


INTERAKT

INTERACTIVE SOUND LIBRARY



USER GUIDE

7 Days Trial

POWERED BY



CONTENTS

1. INTRODUCTION
2. SETUP INSTRUCTIONS
3. CONTROL PANEL
4. SAMPLE BROWSER
5. DROPZONE
6. LAYERS
7. FADE IN/OUT SETTINGS
8. PLUGINS
9. RECORDING
10. PRESETS MANAGER
11. MIDI MAPPING
12. SHORTCUTS
13. SOUND PACKS
14. AUDIO SETTINGS
15. OUTPUT ROUTING
16. SYSTEM REQUIREMENTS

1 | INTRODUCTION

Interakt is an interactive sound library used for editing, recording and playing sounds in real-time. It's a tool that makes it possible to bring any sound alive! Enhance your sound libraries with another way to design, record and export a variety of audio works in many files at once to make the job faster. Communicate directly with your DAW and record audio samples to then add them easily into a project in order to increase productivity of editing tasks.

2 | SETUP INSTRUCTIONS

IMPORTANT: Always use this software under Admin account.
It needs to be located in the same hard drive containing your OS.

MAC:

Copy Interakt folder within your applications folder. Double-click Interakt app.

IMPORTANT: Some Mac OSX users will receive a "file damaged" message when trying to run the software: this is caused by GateKeeper, a security feature set by default in your OSX. Please refer to "**IMPORTANT For Mac Users**" pdf file to solve this issue.

WINDOWS:

Copy Interakt folder within your program files folder. Double-click Interakt.exe.

3 | LIMITATIONS

7-Days Trial

This demo version will expire in 7 days after activating the trial.

Recording disabled

The recording feature is impossible in the demo version. Please buy the full version to enjoy this function.

Export disabled

It's not possible to export any files with the demo version. Please buy the full version to enjoy this function.


Batch Export disabled

It's not possible to export any files with the demo version. Please buy the full version to enjoy this function.

Preset save/load disabled

The presets section is restricted in the demo version. Please buy the full version to enjoy this section.


4 | CONTROL PANEL



- **Batch Export:** Export all sound selections from Dropzone and Layers at the same time in one click.
- **Recording:** Stereo output recording in WAV or AIFF.
- **Preset:** Button to access the Presets manager.
- **Pitch:** Overall pitch control, all the zones and selections will be affected
- **Master:** Volume control, all the zone and selections will be affected
- **Vu Meter:** See and control the real time sound activity

5 | SAMPLE BROWSER

Select any folder from your computer to use the audio files included within this folder and subfolders. **Interakt** works with WAV, AIFF and Mp3 files.



- **Folder.** Choose a folder to be shown within the menu. You can also drag & drop any folder from your computer within the left side window.
- **Autoplay.** When enabled, the selected audio file from the audio files browser will be previewed automatically. If disabled, you'll need to click the play button next to each audio file.
- **Transfer:** Send the selected audio file to the desired section (Dropzone & Layers 1 to 4). You can also drag & drop any audio file from the browser to the desired section.

The Sample Browser will always remember the folder used last before closing Interakt.

5 | DROPZONE

You can upload audio file from the File button at the left. You can also drag file from the Browser section or drag files from any other folders.

This section allows you to select up to 8 different regions within the Dropzone audio file waveform. Use your mouse to select the start/end of each selection.



- **Selections:** up to 8 waveform regions at the same time. Use keyboard keys “1 to 8” to make the selections. Each selection has a different color associated, you’ll easily recognize the selections within the waveform. A small blue strip shows you which selection number you are editing.
- **Waveform Zoom In/Out:** To get more precise selections within the waveform you can zoom in/out using CMD+click (mouse up+down+left+right) on Mac or CTRL+click on Windows.
- **Selection Scroll:** To move any selection (in terms of time) within the waveform use ALT+click over the chosen selection (mouse left/right) on Windows and Mac.
- **Selection adjust:** To adjust the end point of the selection without moving the start point use SHIFT+click over and (mouse left/right) on Windows and Mac
- **Selection Audio Prelisten:** Use “spacebar” to preview the selection. It will preview the selection you’re editing (1 to 8). If you want to preview the whole audio file just use keyboard key “0” and press the spacebar.
- **File Specs:** The file specs section will show the sampling rate, bit depth, channels and duration (in ms) of the dropzone audio file.
- **Playback:** You can play the audio selections using your computer keyboard or a midi keyboard. Each selection has an associated computer key.



1. Computer Keyboard “q”
2. Computer Keyboard “w”
3. Computer Keyboard “e”
4. Computer Keyboard “r”
5. Computer Keyboard “t”
6. Computer Keyboard “y”
7. Computer Keyboard “u”
8. Computer Keyboard “i”

- **Midi Keyboard Assign:** You can assign the playback of any selection to any key within C3 & C4 octaves from your midi keyboard. Each selection can be assigned to only 1 key, but you can assign 2 (or more) different selections to the same key.

To assign a selection to a midi keyboard key just click on the desired key within the virtual keyboard, located just below the dropzone waveform. The chosen key will have the same color as the associated selection.


A small red led placed on each virtual keyboard key will show you which midi keyboard keys are pressed.

You can select which midi device you want to use within the audio settings window.


- **Pitch Wheel:** You can use the pitch wheel from your midi keyboard or the virtual keyboard. Pitch wheel ranges from -6/+6 semitones.



- **Reset:** There are 2 reset buttons available within the dropzone. One for waveform selections and another one for associated keyboard keys at the virtual keyboard.




- **Transfer to Layers:** Send the chosen selection to Layers 1 to 4. First, choose the desired Layer section to transfer the selection and then click on "Transfer".



- **File:** Load to Dropzone any file from your computer without using the browser section.
- **Normalize:** Normalize the volume to -0.1 TruePeak



- **Selection Panel:** This section placed next to Dropzone waveforms shows you:



1. Color Selection.
2. Selection Time (in ms).
3. **Loop** enable/disable: Playback in loop mode while pressing the associated key.
4. **Reverse:** Reverse playback
5. **Export:** Export the selection in WAV, AIFF, or FLAC format.
6. Selection Gain Control: Set the volume of the selection.
7. Clipping indicator: It turns red if the selected output is clipping.

6 | LAYERS

You can also drag file from the Browser section or drag files from any other folders.

There are up to 4 different layers sections available.



Any waveform selection/audio file can be transferred to Layers using the “Transfer” button placed on Browser and Dropzone sections (you must first select to which Layer you want to transfer the waveform selection/audio file). Audio files can also be transferred to Layers from the Browser section using drag & drop to the chosen Layer section.

- **Normalize:** Normalize the volume to -0.1 TruePeak
 - **Reverse:** Reverse playback
 - **Pitch:** Set the playback pitch +/- 6 semitones. Double-Click over the semitones values to reset it to zero.
 - **Pan:** Pan Layer output left/right. Double-Click over the panorama value to reset it to the center.
 - **Gain:** Set the layer output gain. Double-Click over the volume value to reset it to zero.
 - **Clip:** Clipping indicator.
 - **Loop:** Enable/disable loop playback.
 - **Assign:** This lets you assign the midi associated key within the virtual keyboard.
 - **Clear:** Remove the sound from the Layer.
 - **Export:** Export the Layer selection in WAV, AIFF, or FLAC format.
 - **Preview:** Pre-listen to the Layer waveform selection.
-
- **Playback:** You can play the audio selections using your computer keyboard. Each layer has an associated computer key.

Layer 1 - Computer Keyboard “a”


Layer 2 - Computer Keyboard “s”

Layer 3 - Computer Keyboard “d”

Layer 4 - Computer Keyboard “f”

6.1 | PITCH ENVELOPES [CMD+E (Mac)/CTRL+E (Windows)]

The Pitch envelopes section allows you to create dynamic pitch envelopes on each Layer (+/- 6 semitones). The waveform will show you only the selection made within the Layer section.




- **On/Off:** Enable/disable pitch envelope.
- **R:** Reset pitch envelope.
- **Always On Screen:** Enable always on top Pitch Envelopes window.

How it works:

- Click in empty space to add a new envelope point.
- Shift-click over any envelope point to remove it.


7 | FADE IN & OUT SETTINGS

Set the playback fade in/out for each Dropzone selection and Layers 1 to 4 in ms. By default, all playable sections have a 20ms fade in/out to avoid click/noise coming from the start/end selection on Dropzone and Layers.



8 | PLUGINS

Process audio output through up to 2 effect plugins (VST & AU). Only 64Bit plugins.



Plugin 1 & 2. Select a VST/au plugin from your computer.

View. Show plugin on screen. [CMD+1/2 (Mac)| CTRL+1/2 (Windows)]

Load Preset. Load a plugin internal preset. (.fxp file)

Bypass. Bypass plugin.

Remove. Remove plugin.

9 | RECORDING

Stereo output recording in WAV or AIFF (16/24/32Bits). Up to 192kHz (depending on your soundcard). Please follow these guidelines for each recording take.

- Set Bit Depth within the top menu Recording tab.
- The sampling rate is the same used for Interakt. You can change it via Audio Settings.
- Press REC (CMD+R on Mac/CTRL+R on Windows) to start recording. The recording will start automatically after selecting the destination folder/filename.
- Press STOP to stop the recording (CMD+T on Mac/CTRL+T on Windows).


9.1 | BATCH EXPORT [CMD+B (Mac)/CTRL+B (Windows)]

Export all sound selections from Dropzone and Layers at the same time in one click.

- Set the extension (WAV, AIFF) within the save window

10 | PRESETS MANAGER

Load the Interakt bank presets or save your own.



- **Folder.** Choose a folder to be shown within the menu. You can also drag & drop any folder from your computer within the left side window.

- **Save.** Save a preset.

If the audio files used for a preset are moved to another location within your computer, Interakt may not find these files to load the preset properly. In this case, we recommend you to find the files manually within your computer, drop the audio files to the right section (Dropzone or Layers) and load the preset again (and save it again too).

- **Load.** Load a preset.
- **R.** Reset to the default setup.


The Preset Manager section will always remember the folder used last before closing Interakt.

11 | MAPPING


Midi control for master gain (+master pitch) and pitch, pan and gain, both dropzone and layers.

Allow to set any midi knob to change setting within the midi keyboard or controller.

Activate the MIDI Mapping pushing the SETUP button in the Audio Setting Tab. (Ctrl+A)



The Interakt panel will be show like that. Allow to link the setting section to the midi controller.



Press **ESC** to quit the MIDI Mapping configuration

12 | KEYBOARD SHORTCUTS

For better and faster user experience.

DROPZONE

- 1 – Edit Dropzone selection 1
- 2 – Edit Dropzone selection 2
- 3 – Edit Dropzone selection 3
- 4 – Edit Dropzone selection 4
- 5 – Edit Dropzone selection 5
- 6 – Edit Dropzone selection 6
- 7 – Edit Dropzone selection 7
- 8 – Edit Dropzone selection 8
- 0 – Select the whole audio file for preview using the spacebar
- Spacebar** – Prelisten selection in edit mode

LAYERS

CMD+E (Mac) / CTRL + E (Windows) – Open Layers Pitch Envelopes

PLUGINS:

CMD + 1 (Mac) / CTRL + 1 (Windows) – See Plugin 1 on screen

CMD + 2 (Mac) / CTRL + 2 (Windows) – See Plugin 2 on screen

RECORDING

CMD + R (Mac) / CTRL + R (Windows) – Start Recording

CMD + T (Mac) / CTRL + T (Windows) – Stop Recording

CMD + B (Mac) / CTRL + B (Windows) – Batch Export

GENERAL

CMD + A (Mac) / CTRL + A (Windows) – Open Audio Settings

CMD + F (Mac) / CTRL + F (Windows) – Open Fades Settings

CMD + P (Mac) / CTRL + P (Windows) – Open Presets Manager

CMD + U (Mac) / CTRL + U (Windows) – Open User Guide

13 | SOUND PACKS

If you have purchased extra sound packs from Mechanical Wave SFX please follow these guidelines before using the sound packs/presets:

Copy the audio files from the sound packs within:


- For Windows, Interakt/resources/sound packs.
- For Mac, Interakt/Contents/Resources/sound packs (Right-Click on Interakt.app and select “Show Package Content”)

The preset file (.json) can be stored at any location within your computer.

To buy more Presets and Sound Packs visit: <https://mechanicalwavesfx.com/pages/interakt>

13 | AUDIO SETTINGS [CMD+A (Mac) / CTRL+A (Windows)]

In this section, you can set your audio and midi settings.



If you have problems with the sound (clicks/distortion) try changing IO Vector Size and Signal Vector Size to lower values.

Default Output setup:

Main Out – Soundcard Outputs 1(L) & 2(R).

14 | OUTPUT ROUTING

Send audio from Interakt to any other software for recording. We strongly recommend BlackHole (Mac) and Jack Audio (Mac/Windows).

BlackHole:

<https://github.com/ExistentialAudio/BlackHole>

Jack Audio:

<https://jackaudio.org/downloads/>

For more info and tutorial to see how to connect them, visit:

<https://mechanicalwavesfx.com/pages/interakt-tutorials>

15 | SYSTEM REQUIREMENTS

Mac System Requirements

- Mac Intel Machine running OS X 10.11.6 or Later. 64 Bits. 4GB Recommended.
- Apple ARM machine running OS X 11.0 or Later. 64 Bits. 4GB Recommended.

Users do not need to use Rosetta anymore, Interakt also works on Apple ARM computers as a native app.

Windows System Requirements

- Windows 8 and Windows 10, Multicore processor. Intel 64 Bits. Minimum RAM 4GB.

Technical support:

<https://mechanicalwavesfx.com/pages/contact>

MECHANICAL WAVE